# **PTable Documentation**

Release 0.9.0

**Kane Blueriver** 

## Contents

1 Links 3

 $PTable \ is \ a \ simple \ Python \ library \ designed \ to \ make \ it \ quick \ and \ easy \ to \ represent \ tabular \ data \ in \ visually \ appealing \ ASCII \ tables, \ originally \ forked \ from \ Pretty Table \ .$ 

Contents 1

2 Contents

## CHAPTER 1

Links

- Source Code (GitHub)
- PyPI
- RTFD

## 1.1 Installation

PTable is published on PyPI, so you can easily install it via pip or easy\_install, and pip is recommended:

```
pip install PTable
```

or:

easy\_install PTable

## 1.1.1 Command Line Usage

Command Line support is included since version 0.9.0, it pretty easy:

```
ptable --csv=filename.csv
```

will print result in the console, you can save it to file by:

```
ptable --csv=filename.csv > filename.txt
```

## 1.1.2 Installation

PTable is published on PyPI, so you can easily install it via pip or easy\_install, and pip is recommended:

```
pip install PTable
```

or:

```
easy_install PTable
```

#### 1.1.3 Tutorial

This tutorial is distributed with PrettyTable and is meant to serve as a "quick start" guide for the lazy or impatient. It is not an exhaustive description of the whole API, and it is not guaranteed to be 100% up to date. For more complete and update documentation, check the PrettyTable wiki at http://code.google.com/p/prettytable/w/list

#### Getting your data into (and out of) the table

Let's suppose you have a shiny new PrettyTable:

```
from prettytable import PrettyTable
x = PrettyTable()
```

and you want to put some data into it. You have a few options.

#### Row by row

You can add data one row at a time. To do this you can set the field names first using the field\_names attribute, and then add the rows one at a time using the add\_row method:

```
x.field_names = ["City name", "Area", "Population", "Annual Rainfall"]
x.add_row(["Adelaide",1295, 1158259, 600.5])
x.add_row(["Brisbane",5905, 1857594, 1146.4])
x.add_row(["Darwin", 112, 120900, 1714.7])
x.add_row(["Hobart", 1357, 205556, 619.5])
x.add_row(["Sydney", 2058, 4336374, 1214.8])
x.add_row(["Melbourne", 1566, 3806092, 646.9])
x.add_row(["Perth", 5386, 1554769, 869.4])
```

#### Column by column

You can add data one column at a time as well. To do this you use the add\_column method, which takes two arguments - a string which is the name for the field the column you are adding corresponds to, and a list or tuple which contains the column data"

```
x.add_column("City name",
  ["Adelaide", "Brisbane", "Darwin", "Hobart", "Sydney", "Melbourne", "Perth"])
x.add_column("Area", [1295, 5905, 112, 1357, 2058, 1566, 5386])
x.add_column("Population", [1158259, 1857594, 120900, 205556, 4336374, 3806092, 1554769])
x.add_column("Annual Rainfall", [600.5, 1146.4, 1714.7, 619.5, 1214.8, 646.9, 869.4])
```

#### Mixing and matching

If you really want to, you can even mix and match add\_row and add\_column and build some of your table in one way and some of it in the other. There's a unit test which makes sure that doing things this way will always work out nicely as if you'd done it using just one of the two approaches. Tables built this way are kind of confusing for other people to read, though, so don't do this unless you have a good reason.

#### Importing data from a CSV file

If you have your table data in a comma separated values file (.csv), you can read this data into a PrettyTable like this:

```
from prettytable import from_csv
fp = open("myfile.csv", "r")
mytable = from_csv(fp)
fp.close()
```

#### Importing data from a database cursor

If you have your table data in a database which you can access using a library which confirms to the Python DB-API (e.g. an SQLite database accessible using the sqlite module), then you can build a PrettyTable using a cursor object, like this:

```
import sqlite3
from prettytable import from_db_cursor

connection = sqlite3.connect("mydb.db")
cursor = connection.cursor()
cursor.execute("SELECT field1, field2, field3 FROM my_table")
mytable = from_db_cursor(cursor)
```

#### Getting data out

There are three ways to get data out of a PrettyTable, in increasing order of completeness:

- The del\_row method takes an integer index of a single row to delete.
- The clear\_rows method takes no arguments and deletes all the rows in the table but keeps the field names as they were so you that you can repopulate it with the same kind of data.
- The clear method takes no arguments and deletes all rows and all field names. It's not quite the same as creating a fresh table instance, though style related settings, discussed later, are maintained.

#### Displaying your table in ASCII form

PrettyTable's main goal is to let you print tables in an attractive ASCII form, like this:

```
+-----+
| City name | Area | Population | Annual Rainfall |
+-----+
| Adelaide | 1295 | 1158259 | 600.5 |
| Brisbane | 5905 | 1857594 | 1146.4 |
| Darwin | 112 | 120900 | 1714.7 |
```

(continues on next page)

(continued from previous page)

1	Hobart		1357		205556		619.5	
	Melbourne		1566		3806092		646.9	
1	Perth		5386		1554769		869.4	
	Sydney		2058		4336374		1214.8	
+-		-+-		-+-		+-		+

You can print tables like this to stdout or get string representations of them.

#### **Printing**

To print a table in ASCII form, you can just do this:

```
print x
```

in Python 2.x or:

```
print(x)
```

in Python 3.x.

The old x.printt() method from versions 0.5 and earlier has been removed.

To pass options changing the look of the table, use the get\_string() method documented below:

```
print x.get_string()
```

#### **Stringing**

If you don't want to actually print your table in ASCII form but just get a string containing what *would* be printed if you use "print x", you can use the <code>get\_string</code> method:

```
mystring = x.get_string()
```

This string is guaranteed to look exactly the same as what would be printed by doing "print x". You can now do all the usual things you can do with a string, like write your table to a file or insert it into a GUI.

#### Controlling which data gets displayed

If you like, you can restrict the output of print x or x.get\_string to only the fields or rows you like.

The fields argument to these methods takes a list of field names to be printed:

```
print x.get_string(fields=["City name", "Population"])
```

gives:

```
+-----+
| City name | Population |
+-----+
| Adelaide | 1158259 |
| Brisbane | 1857594 |
| Darwin | 120900 |
```

(continues on next page)

(continued from previous page)

The start and end arguments take the index of the first and last row to print respectively. Note that the indexing works like Python list slicing - to print the 2nd, 3rd and 4th rows of the table, set start to 1 (the first row is row 0, so the second is row 1) and set end to 4 (the index of the 4th row, plus 1):

```
print x.get_string(start=1,end=4)
```

#### prints:

```
+-----+
| City name | Area | Population | Annual Rainfall |
+-----+
| Brisbane | 5905 | 1857594 | 1146.4 |
| Darwin | 112 | 120900 | 1714.7 |
| Hobart | 1357 | 205556 | 619.5 |
+------+
```

#### Changing the alignment of columns

By default, all columns in a table are centre aligned.

#### All columns at once

You can change the alignment of all the columns in a table at once by assigning a one character string to the align attribute. The allowed strings are "l", "r" and "c" for left, right and centre alignment, respectively:

```
x.align = "r"
print x
```

#### gives:

+	+	+		+		+
			-		ual Rainfall	
+	+	+		+		+
Adelaide	129	5	1158259		600.5	
Brisbane	590	5	1857594		1146.4	
Darwin	11	2	120900		1714.7	
Hobart	135	7	205556		619.5	
Melbourne	156	6	3806092		646.9	
Perth	538	6	1554769		869.4	
Sydney	205	8	4336374		1214.8	
+	+	+		+		+

#### One column at a time

You can also change the alignment of individual columns based on the corresponding field name by treating the align attribute as if it were a dictionary.

```
x.align["City name"] = "1"
x.align["Area"] = "c"
x.align["Population"] = "r"
x.align["Annual Rainfall"] = "c"
print x
```

#### gives:

#### Sorting your table by a field

You can make sure that your ASCII tables are produced with the data sorted by one particular field by giving get\_string a sortby keyword argument, which > must be a string containing the name of one field.

For example, to print the example table we built earlier of Australian capital city data, so that the most populated city comes last, we can do this:

```
print x.get_string(sortby="Population")
```

#### to get

If we want the most populated city to come first, we can also give a reversesort=True argument.

If you always want your tables to be sorted in a certain way, you can make the setting long term like this:

```
x.sortby = "Population"
print x
print x
print x
```

All three tables printed by this code will be sorted by population (you could do x.reversesort = True as well, if you wanted). The behaviour will persist until you turn it off:

```
x.sortby = None
```

If you want to specify a custom sorting function, you can use the <code>sort\_key</code> keyword argument. Pass this a function which accepts two lists of values and returns a negative or positive value depending on whether the first list should appeare before or after the second one. If your table has n columns, each list will have n+1 elements. Each list corresponds to one row of the table. The first element will be whatever data is in the relevant row, in the column specified by the <code>sort\_by</code> argument. The remaining n elements are the data in each of the table's columns, in order, including a repeated instance of the data in the <code>sort\_by</code> column.

#### Changing the appearance of your table - the easy way

By default, PrettyTable produces ASCII tables that look like the ones used in SQL database shells. But if can print them in a variety of other formats as well. If the format you want to use is common, PrettyTable makes this very easy for you to do using the set\_style method. If you want to produce an uncommon table, you'll have to do things slightly harder (see later).

#### Setting a table style

You can set the style for your table using the set\_style method before any calls to print or get\_string. Here's how to print a table in a format which works nicely with Microsoft Word's "Convert to table" feature:

```
from prettytable import MSWORD_FRIENDLY
x.set_style(MSWORD_FRIENDLY)
print x
```

In addition to MSWORD\_FRIENDLY there are currently two other in-built styles you can use for your tables:

- DEFAULT The default look, used to undo any style changes you may have made
- $\bullet \ \mathtt{PLAIN\_COLUMNS} \ \ A \ borderless \ style \ that \ works \ well \ with \ command \ line \ programs \ for \ columnar \ data \\$

Other styles are likely to appear in future releases.

### Changing the appearance of your table - the hard way

If you want to display your table in a style other than one of the in-built styles listed above, you'll have to set things up the hard way.

Don't worry, it's not really that hard!

#### Style options

PrettyTable has a number of style options which control various aspects of how tables are displayed. You have the freedom to set each of these options individually to whatever you prefer. The set\_style method just does this automatically for you.

The options are these:

- border A boolean option (must be True or False). Controls whether >> or not a border is drawn around the table.
- header A boolean option (must be True or False). Controls whether >> or not the first row of the table is a header showing the names of all the >> fields.

- hrules Controls printing of horizontal rules after rows. Allowed >> values: FRAME, HEADER, ALL, NONE note that these are variables defined >> inside the prettytable module so make sure you import them or use >> prettytable.FRAME etc.
- vrules Controls printing of vertical rules between columns. Allowed >> values: FRAME, ALL, NONE.
- int\_format A string which controls the way integer data is printed. >> This works like: print "%<int\_format>d" % data
- float\_format A string which controls the way floating point data is >> printed. This works like: print "%<int format>f" % data
- padding\_width Number of spaces on either side of column data (only used > > if left and right paddings are None).
- left\_padding\_width Number of spaces on left hand side of column data.
- right\_padding\_width Number of spaces on right hand side of column data.
- vertical\_char Single character string used to draw vertical lines. >> Default is |.
- horizontal\_char Single character string used to draw horizontal lines. >> Default is -.
- junction\_char Single character string used to draw line junctions. >> Default is +.

You can set the style options to your own settings in two ways:

#### Setting style options for the long term

If you want to print your table with a different style several times, you can set your option for the "long term" just by changing the appropriate attributes. If you never want your tables to have borders you can do this:

```
x.border = False
print x
print x
print x
```

Neither of the 3 tables printed by this will have borders, even if you do things like add extra rows inbetween them. The lack of borders will last until you do:

```
x.border = True
```

to turn them on again. This sort of long term setting is exactly how set\_style works. set\_style just sets a bunch of attributes to pre-set values for you.

Note that if you know what style options you want at the moment you are creating your table, you can specify them using keyword arguments to the constructor. For example, the following two code blocks are equivalent:

```
x = PrettyTable()
x.border = False
x.header = False
x.padding_width = 5
```

x = PrettyTable(border=False, header=False, padding\_width=5)

#### Changing style options just once

If you don't want to make long term style changes by changing an attribute like in the previous section, you can make changes that last for just one get\_string by giving those methods keyword arguments. To print two "normal"

tables with one borderless table between them, you could do this:

```
print x
print x.get_string(border=False)
print x
```

#### Displaying your table in HTML form

PrettyTable will also print your tables in HTML form, as s. Just like in ASCII form, you can actually print your table - just use print\_html() - or get a string representation - just use get\_html\_string(). HTML printing supports the fields, start, end, sortby and reversesort arguments in exactly the same way as ASCII printing.

#### Styling HTML tables

By default, PrettyTable outputs HTML for "vanilla" tables. The HTML code is quite simple. It looks like this:

```
City name
    Area
    Population
    Annual Rainfall
  Adelaide
    1295
    1158259
    600.5
  \langle t.r \rangle
    Brisbane
    5905
    1857594
    1146.4
  . . .
  . . .
```

If you like, you can ask PrettyTable to do its best to mimick the style options that your table has set using inline CSS. This is done by giving a format=True keyword argument to either the print\_html or get\_html\_string methods. Note that if you *always* want to print formatted HTML you can do:

```
x.format = True
```

and the setting will persist until you turn it off.

Just like with ASCII tables, if you want to change the table's style for just one print\_html or one get\_html\_string you can pass those methods keyword arguments - exactly like print and get\_string.

#### **Setting HTML attributes**

You can provide a dictionary of HTML attribute name/value pairs to the print\_html and get\_html\_string methods using the attributes keyword argument. This lets you specify common HTML attributes like name, id

and class that can be used for linking to your tables or customising their appearance using CSS. For example:

```
x.print_html(attributes={"name":"my_table", "class":"red_table"})
```

will print:

## Miscellaneous things

### Copying a table

You can call the copy method on a PrettyTable object without arguments to return an identical independent copy of the table.

If you want a copy of a PrettyTable object with just a subset of the rows, you can use list slicing notation:

```
new_table = old_table[0:5]
```